

Release for Production



		SOFTWARE	
Change Notification (AE)	Scope: Global Production	No.: AE141_2024	

Distribution	G	SL	PD	PDM	OM	QA	ENH Lorenz Laden- burger	RD	SE	PP	PM	ENH	EN	AE	RDL	RDE	RDA	Total	
Sheet 1			X			X	X	X	X		X		X	X	X		X	X	10
Serial Sheet																			

Software for Measurement Card S169263-233

CellTek-SW

- Software: S169263-233 from 16.12.2024, Revision R14012 (60eba7)
- Required OS: S169258-1.1 from 16.10.2024, Revision 1406
- Git Tag: S169263-231-14012
- Development Environment: devenv:1.2.3

Main Changes / Enhancements to Version 232:

- PRR-18567 - Error GCOM occurs if the start switch is released during the dwell-time when gyro is attached
- PRR-22568 - CellTek-PINs are not always written with Cordless RF Configuration.
- PRR-23343 - Removing gyro during rundown - rundown is not immediately NOK with GCOM error.
- PRR-23358 - Not possible to install WLAN certificates for WLAN connections.
- PRR-23393 - Reverse application not working with 2 or more stages.

Known issues:

- PRR-23415 - Emergency mode - Tool locked when emergency mode is activated with scanner during job

Target Hardware:	mPro400SG/GC	mProConnect	PC (Windows)
	mPro300	PDMI	X CellTek
	Other:		
Link to GIT/SVN:	http://eugitlab.atg.root/VYB/stmd/-/tags/release/S169263-233-14012		

For request to:					
AE	X	- for consideration at new disposition	SE	X	- for consideration at service benefits
		- first consume old stock	SL		- information to all external agent representatives
		- rework stock	EN		- creating material data in SAP
	X	- for consideration at operation	PD		- ordering
X	- information to all mechanics			- current orders	
RDS / ENS / ENH	X	- for consideration at new conception			- debut price
	X	- for consideration at software duplication	RDL		- update test beds
		- update test beds			

	Editor:	Auditor:	Inspector:	Approval:	Order number:
Date	19.12.2024	07.01.2025	19.12.2024	07.01.2025	
Name	Roithmayer, Guenther RDS/ENT	Schips, Patrick RDS/ENT	Opferkuch, Markus RDL	Kogel, Manfred RD/EN	